

TUBEPRO 6 LICENSING

Instructions to activate and manage licenses.

TABLE OF CONTENT



- NEW SUBSCRIPTION
- UPDATE AND SUBSCRIPTION RENEWAL WITH A CLOUD KEY
- UPDATE AND SUBCRIPTION RENEWAL WITH A TP5 HARDKEY
- LICENSE MANAGEMENT
- TRIALS



NEW SUBSCRIPTION


__

PURCHASING A TUBEPRO-6.X

ACTIVATE A NEW SUBSCRIPTION



- 1. Make sure your computer is connected to the internet. This is <u>required</u> to activate a license.
- Launch TubePro
- 3. Access the *Manage License* panel:
 - a) If no valid license is currently activated on this computer, the Manage License panel will automatically open.
 - b) If there is already a valid license (different key or trial) activated on the computer:
 - In the backstage view, click on *License* and then on *License*Manager.
 - II. In the Eddyfi License Manager panel, click on Manage.
- 4. In the *Manage License* panel, input the license code provided by email in the *License Code* field and click *Activate*.





UPDATE AND SUBSCRIPTION RENEWAL WITH A CLOUD KEY


_

PURCHASING A TUBEPRO-6.X-SSP OR TUBEPRO-6.X-CONVERT

RENEW AN EXISTING SUBSCRIPTION



- 1. After the order was processed by Eddyfi, make sure your computer is connected to the internet.
- 2. Launch TubePro
- The license will automatically be refreshed. You can confirm the next Renewal Date at the bottom of the Manage License panel.



In the *Current License Information* panel: if the *Status* field is *Valid* with a green check mark, your license is active.

In the *Current License Information* panel: if the Licensing System field is *Connected* with a green check mark, the software has the required internet access to refresh the license.



UPDATE AND SUBSCRIPTION RENEWAL WITH A TP5 HARDKEY

__

PURCHASING A TUBEPRO-6.X-SSP

MIGRATION PROCEDURE




PART A: DISABLING YOUR HARDWARE KEY (HK)

- 1. Connect your USB dongle to your computer.
- 2. Make sure your computer is connected to the internet.
- 3. Save the executable *MagnifiKeyMigrator.exe* provided by Eddyfi on your computer.

https://eddyfi.com/doc/Software/download/MagnifiKeyMigrator-1.0.exe

- Run the executable.
- 2. After reading the *Warning* message, click *OK* to acknowledge.
 - Note: The new cloud key <u>CANNOT</u> be used to run both softkey and hardkey versions of TubePro. Upon
 deactivating the license on your key, you will lose access to hardkey versions of TubePro.
- 3. Select the license type (TubePro) you want to deactivate.
- Fill out the Contact Information.
- Click the Deactivate button.




MIGRATION PROCEDURE



PART A: DISABLING YOUR HARDWARE KEY (HK)

- 9. Click OK to close the window that confirms the deactivation of the key.
- 10. You will also receive an email confirming that your HK has been deactivated.
- 11. Wait for the email confirming that your new cloud-based license has been updated.




MIGRATION PROCEDURE



PART B: ACTIVATING THE LICENSE

- 12. Open the most recent version of the software.
- 13. Access the *Manage License* panel:
 - a) If no valid license is currently activated on this computer, the
 Manage License panel will automatically open.
 - i. Enter the license code provided by Eddyfi.
 - ii. Click on. Activate.
 - b) If there is already a valid license (trial) activated on the computer:
 - i. At TubePro launch, in the backstage view, click on *License*.
 - ii. In the License page, click on License Manager.
 - iii. In the Eddyfi License Manager panel, click on Manage.
 - iv. In the Manage License, click on Release.
 - v. Enter the license code provided by Eddyfi and click on Activate.





LICENSE MANAGEMENT

_


HOW TO MOVE THE LICENSE TO A DIFFERENT COMPUTER

LICENSE MANAGEMENT



PART A: HOW TO RELEASE FROM A COMPUTER

- 1. Make sure the computer is connected to the internet.
- Launch TubePro.
- 3. In the backstage view, click on *License*.
- 4. In the *License* page, click on *License Manager* icon.
- 5. In the Eddyfi License Manager panel, click on Manage.
- 6. In the Manage License, click on Release.
- 7. Carefully note the license code as it will be required for activation on the second computer.




LICENSE MANAGEMENT



PART B: ACTIVATE ON OTHER COMPUTER

- 1. Make sure your computer is connected to the internet.
- 2. Launch TubePro
- Activate the code on the second PC:
 - a) If no valid license is currently activated on this computer, the *Manage License* panel will automatically open.
 - i. In the Manage License panel, enter the License Code.
 - ii. Click on Activate.
 - b) If there is already a valid license (different key or trial) activated:
 - I. In the backstage view, click on *License* and click on *License Manager*.
 - II. In the Eddyfi License Manager panel, click on Manage.
 - III. In the Manage License panel, enter the License Code released from the first PC.
 - IV. Click on Activate.



Note: After being activated, the *License Code* is saved, and it is no longer necessary to enter it again.



TRIALS

_


7-DAY & 30-DAY TRIAL PERIODS

7-DAY TRIAL



7-day trials are available for anyone but can only be activated once for a given computer on any versions.

- Make sure your computer is connected to the Internet. Once the trial is activated, the computer can be disconnected from the Internet.
- 2. Start the desktop software.
- The Manage License panel will automatically appear on the screen as there is no valid license activated on the computer.
- 4. Click Request Temporary License or Request Trial and fill in the form. The trial will start immediately.




In the *Current License Information* panel: if the *Licensing System* field is *Connected* with a green check mark, the software has the required internet access to activate the license.

30-DAY TRIAL



For 30-day trials, a license code must be provided by a sales representative.

- 1. Make sure your computer is connected to the internet. This is required to activate a license.
- 2. Start the desktop software.
- 3. Access the *Manage License* panel:
 - a) If no valid license is currently activated on this computer, the Manage License panel will automatically open.
 - b) If there is already a valid licence (different key or trial) activated on the computer:
 - I. At TubePro launch, in the backstage view, click on *License*.
 - II. In the License page, click on License Manager.
 - III. In the Eddyfi License Manager panel, click on Manage.
- 4. In the Manage License panel, input the license code provided by email in the License Code field and click Activate.



In the *Current License Information* panel: if the *Status* field is *Valid* with a green check mark, your license is active.