

Eddyfi Magnifi®GO 4.7R10 Release Notes

System Requirements

- Eddyfi Reddy for surface (32/32M, 64/64M or 128/128M)
- Eddyfi Reddy for tubing (AC-E)

Firmware

- Included with this release of Magnifi®GO is firmware version 2.1R5 for surface and tubing instruments.

New Features and Improvements

Generic

- Magnifi Wi-fi update capabilities now included for future software releases
- Improved stability

Surface Applications

- Supports pre-calibrated Spyne™ probes for more uniform signal across the array
- Automated calibration check for array probes
- Calibration (rotation) assistant mode for array probes

Modifications to Existing Features

None in this version

Dropped Features

None in this version

Resolved Issues

- Merge C-scan indication
- Rotation button display issues (button disappearing in some situations) (in Lissajous)

Known Issues, Limitations, and Restrictions

- Cannot save data acquired in Cal.check mode and Lift-off assistant mode
- Use of I-flex probes with impedance topology AND one of SDL or SDD topology simultaneously lowers signal amplitude from the transmit-receive topology (SDL or SDD)
- Specific conditions causing duplication of the data file in data list (creates a second data file (increment file name) but contains the same data)
- Report viewer can't display screenshots
- The report does not work if too many indications/screenshots are included
- Sharck Fillet Weld Probe - Transverse C-scan display too many channels
- Spyne Probe - Y-axis preset must remain to zero in raster scan mode